

preservative, delivered with a disposable infusion device.

Oustric-Mendes AC, Huart B, Le Hoang MD, Perrin-Rosset M, Pailler FM, Darbord JC, Prognon P, Gard C, Pradeau D

Related Resources

Ecole d'Application du Service de Sante des Armees, Chaire de Sciences Pharmaceutiques, Toxicologie et Expertises dans les Armees, Paris, France.

BACKGROUND AND OBJECTIVE: Morphine hydrochloride, a major analgesic drug, is being increasingly administered using portable disposable infusion devices. The objective of this study was to investigate the stability of morphine in such a system at two concentrations (2.50 and 5.00 mg/ ml) over a 30-day period. METHOD: High-performance liquid chromatography of stored morphine solutions. RESULTS: The best stability was observed with disposable infusion devices filled with a morphine solution containing sodium metabisulphite as a preservative. No breakdown products were detected after 1 month of storage at room temperature, in light or darkness. On the other hand, 2.50 and 5.00 mg/ml morphine solutions without sodium metabisulphite, stored in the infusion device led to the formation of 0.205% and 0.235% of pseudomorphine, respectively, after 6 days of storage in the light, and 1.50% and 0.94% after 30 days storage. CONCLUSION: Morphine hydrochloride solutions stored in disposable infusion devices degraded very slowly, particularly when preserved with sodium metabisulphite. The solutions are stable over 5 days, the maximum period of storage normally required when using disposable infusers.

PMID: 9548210, UI: 98207987

|--|

Revised: April 3, 2000.

Disclaimer | Write to the Help Desk




titration

process of chemical analysis in which the quantity of some constituent of a sample is determined by adding to the measured sample an exactly known quantity of another substance with which the desired constituent reacts in a definite, known proportion. The process is usually carried out by gradually adding a standard solution (*i.e.*, a solution of known concentration) of titrating reagent, or titrant, from a burette, essentially a long, graduated measuring tube with a stopcock and a delivery tube at its lower end. The addition is stopped when the equivalence point is reached.

At the equivalence point of a titration, an exactly equivalent amount of titrant has been added to the sample. The experimental point at which the completion of the reaction is marked by some signal is called the end point. This signal can be the colour change of an indicator or a change in some electrical property that is measured during the titration. The difference between the end point and the equivalence point is the titration error, which is kept as small as possible by the proper choice of an end-point signal and a method for detecting it.

For many titration reactions it is possible to find a suitable visual colour indicator that will signal the end point at, or very close to, the equivalence point. Such titrations, classified according to the nature of the chemical reaction occurring between the sample and titrant, include: acid-base titrations, precipitation titrations, complex-formation titrations, and oxidation-reduction (redox) titrations. In acid-base titration (i.e., the titration of an acid with a base, or vice versa), the indicator is a substance that can exist in two forms, an acid form and a basic form, which differ in colour. For example, litmus is blue in alkaline solution and red in acid solution. Phenolphthalein is colourless in acid solution and red in alkaline solution. A wide choice of acid-base indicators is available, varying not only in the colours of the two forms but also in their sensitivity toward acid or base.



Precipitation titrations may be illustrated by the example of the determination of chloride content of a sample by titration with silver nitrate, which precipitates the chloride in the form of silver chloride. The presence of the first slight excess of silver ion (i.e., the end point) can be marked by the appearance of a coloured precipitate. One way in which this can be done is by employing potassium chromate as indicator. Potassium chromate reacts with the first slight excess silver ion to form a red precipitate of silver chromate. Another method involves the use of an adsorption indicator, the indicator action being based on the formation on the surface of the precipitate of an adsorbed layer of silver indicator salt, which forms only when an excess of silver ion is present.


The most important titrations based upon complex-formation reactions are those involving the titration of metal ions with the reagent **disodium** ethylenediaminetetraacetate (a salt of edetic acid, or EDTA). The indicators are dyes that have the property of forming a coloured complex with the metal ion. As the titration proceeds, the reagent reacts first with uncomplexed metal ions, and, finally, at the end point it reacts with the metal-indicator complex. The colour change corresponds to the conversion of the metal-dye complex into the free dye.

In oxidation-reduction (redox) titrations the indicator action is analogous to the other types of visual colour titrations. In the immediate vicinity of the end point, the indicator undergoes oxidation or reduction, depending upon whether the titrant is an oxidizing agent or a reducing agent. The oxidized and reduced forms of the indicator have distinctly different colours.

Alternatively, for many titrations the end point can be detected by electrical measurements. These titrations may be classified according to the electrical quantity that is measured.

Potentiometric titrations involve the measurement of the potential difference between two electrodes of a cell; conductometric titrations, the electrical conductance or resistance; amperometric titrations, the electric current passing during the course of the titration; and coulometric titrations, the total quantity of electricity passed during the titration. In the four titrations just mentioned, except coulometric titrations, the end point is indicated by a marked change in the electrical quantity that is being measured. In coulometric titrations, the quantity of electricity required to carry out a known reaction is measured, and from Faraday's law the quantity of material present is calculated.

INTERNET LINKS




Search for related Internet links that use the term "titration".

INDEX ENTRY

Information about this topic in other articles

titration (chem. process)

- analysis of
 - o <u>blood</u>
 - o halogens
 - <u>lubricants</u>
 - o proteins
- study of
 - o chemical reactions
 - salinity
- use in instrumental chemical analysis
 - in analysis
 - in <u>Classical quantitative analysis</u> from analysis
 - in <u>Infrared spectrophotometry</u> from analysis



"titration" Encyclopædia Britannica Online. http://www.search.eb.com/bol/topic?eu=74558&sctn=1 [Accessed 19 April 2000].

Copyright © 1994-2000 Encyclopædia Britannica, Inc.

